

About LS Studio...

1 LS Studio?


LS Studio is an integrated installation package of XG5000, XP-Builder, and DriveView7 software provided by LSIS.

LS Studio integrated installation package allows you to install or uninstall XG5000, XP-Builder, and DriveView7 collectively or individually.




2 Project file integration management

In XG5000 installed through LS Studio, XP-Builder and DriveView7 projects are managed as a single file.




3 Enhanced variable sharing

Variable sharing between XG5000 and XP-Builder can be used immediately without any separate export / import operation.



<Existing method of variable sharing>



<Variable Sharing Method in Integrated Environment>

4 Conditions for integrated environment

To use the project integration environment, you can use the LS Studio integration package or separately install the XG5000, XP-Builder, and DriveView7 which provide integrated environment functions.



Install LS Studio

or



Install individual S/W

the minimum version required for individual installation is as follows.

S/W	Version
XG5000	V4.11 or later
XP-Builder	V2.00(B27) or later
DriveView7	V1.4.2 or later